


Overall Flow:



Prerequisites:

1. Generating a Hardware ID

1. Navigate to the Artifacts folder in your root directory.
2. Open the HardwareId Generator folder.
3. Double-click on MxFace.SDK.DeviceIdGenerator.exe.
4. Note down the generated Hardware ID displayed in the format:

Example: Generated Device Id:

MQAS5AGX3VWKYGH9ZNR07EHSA4BMDKE0JDXH7WQGAH8WH33BJ8W0

2. Activating License Files

1. Navigate to the Artifacts folder in your root directory.
2. Open Command Prompt as **Run As Administrator**.
3. Copy the path of the IdGen folder (e.g., D:\Activation\IDGen) and change the Command Prompt directory to this folder using:

Ex: `cd /d D:\Activation\IDGen`

4. Ensure the IdGen folder contains `id_gen.exe` and `sn.txt` files.
5. Run the following command in Command Prompt:

`id_gen.exe sn.txt hardware.id`

6. Provide the retrieved **Hardware ID** to us for generating your License File.
7. Navigate back to the **Activation** folder in Command Prompt using:

`cd ..`

8. Once in the Activation folder, run the command:

`pg.exe -install`

Cloning the Sample Project from GitHub

1. Clone the sample project from GitHub.
2. Open the cloned project in **Visual Studio/Visual Studio Code**.
3. Open the terminal and run:

`dotnet build`

4. Open the **Project Folder** in File Explorer and navigate to:

`\Artifacts\Activation\bin`

5. Copy all **DLL** files from this folder.
6. Navigate to:

`\bin`

7. Paste all copied DLL files here.
8. You will receive a **license file** named `Fingerprint.lic`. Place this file in the **bin** folder where you just pasted the DLL files.

Activating the Windows Service

1. Navigate to Artifacts/Activation/Windows Service.
2. Double-click on MFScanClientService.
3. When prompted with **Yes/No**, click **Yes** to install the service.
4. If you are using the **MIS100V2 Fingerprint Device**, install its drivers from:

[Artifacts/Activation/Drivers](#)

Database Setup:

You need to connect to Database in order to enroll, search and match fingerprints.

Let's set up the Database in your system:

1. Install ODBC Driver:
 - a. If you're using PostgreSQL database, download "**psqlodbc_x64.msi**" from https://www.postgresql.org/ftp/odbc/releases/REL-17_00_0004-mimalloc/
 - b. If you're using MySQL database, download "Windows (x86, 64-bit), MSI Installer" from <https://dev.mysql.com/downloads/connector/odbc/>
 - c. If you're using MsSQL database, click on "Download Microsoft ODBC Driver 18 for SQL Server (x64)" from <https://learn.microsoft.com/en-us/sql/connect/odbc/download-odbc-driver-for-sql-server?view=sql-server-ver16>
2. After installing driver for your database, double click on Newley installed application and set it up.
3. Then, press Windows button on your keyboard and type "odbc Data Sources (64-bit)" and open the application.
4. Click on the Add button on the right side on odbc, Select a driver named: PostgreSQL ANSI(x64)
5. Add your database configuration and Test the connection.
6. If Successful, create the below table on your database by running below query:

```
CREATE TABLE IF NOT EXISTS public."__FingerprintSubjects"  
(  
    "Id" integer NOT NULL,  
    "SubjectId" character varying(45) COLLATE pg_catalog."default",  
    "Template" bytea,  
    "Group" character varying(45) COLLATE pg_catalog."default",  
    "ClientId" integer,  
    CONSTRAINT "__FingerprintSubjects_pkey" PRIMARY KEY ("Id")  
)  
  
TABLESPACE pg_default;  
  
ALTER TABLE public."__FingerprintSubjects"  
    OWNER to sa;
```

And you're ready to enroll, search and match fingerprints 😊

Interfaces Overview:

The **MxFace Fingerprint SDK** provides comprehensive fingerprint management capabilities through three main interfaces:

- **ISearch**
- **IDevice**
- **ICaptureService**

This documentation details each interface and its methods.

Interface Details

ISearch Interface

Handles core fingerprint operations including enrollment, verification, and searching.

Enroll Method

Task Enroll(byte[] source, string externalId, string group)

Purpose: Stores a new fingerprint in the database for future matching.

Parameters:

- source: Raw fingerprint image data in bytes.
- externalId: Unique identifier for the fingerprint record.
- group: Organizational group identifier for categorization.

Returns:

- EnrollmentResponse object containing:
 - Success status (200 for success, 400 for duplicates).
 - Detailed result message.
 - Error information if applicable.

Key Features:

- Duplicate checking before enrollment.
- License validation.
- Group-based organization.
- Comprehensive error handling.

Verify Method

Task Verify(byte[] source, byte[] target)

Purpose: Performs direct comparison between two fingerprint samples.

Parameters:

- source: First fingerprint data for comparison.
- target: Second fingerprint data to compare against.

Returns:

- MatchResponse containing:
 - Matching score.
 - Status message.
 - Error code if applicable.

Features:

- One-to-one comparison.
- Quality-based matching.
- Detailed score reporting.

Search Method

```
Task<List> Search(byte[] source, string group)
```

Purpose: Searches database for matching fingerprints.

Parameters:

- source: Fingerprint data to search for.
- group: Optional group filter for targeted searching.

Returns:

- List<SearchResponse> objects containing:
 - Matching scores.
 - Up to 5 best matches.
 - Match details.

Features:

- Group filtering capability.
- Multiple match support.
- Score-based result ranking.

IDevice Interface

Manages fingerprint devices.

GetConnectedDevices Method

Task GetConnectedDevices(List devices)

Purpose: Identifies all physically connected fingerprint devices.

Parameters:

- devices: List to be populated with connected device names.

Returns:

- Number of connected devices found.

Features:

- Real-time device detection.
- Connection status validation.
- Device name parsing.

GetSupportedDevices Method

Task GetSupportedDevices(List deviceList)

Purpose: Lists all supported device models.

Parameters:

- deviceList: List to be populated with supported device names.

Returns:

- Count of supported devices.

Features:

- Model compatibility checking.
- Support validation.
- Comprehensive device listing.

Init Method

Task Init(string productName)

Purpose: Initializes specified fingerprint device.

Parameters:

- productName: Name/model of device to initialize.

Returns:

- 0: Successful initialization.
- -1: Initialization failure.

Features:

- Device-specific initialization.
- Error handling.
- License validation.

GetDeviceInfoAsync Method

Task GetDeviceInfoAsync(string deviceName)

Purpose: Retrieves detailed device information.

Parameters:

- deviceName: Target device name.

Returns:

- Device object containing:
 - Error code.
 - Device specifications.
 - Status information.

Features:

- Detailed device diagnostics.
- Connection status checking.
- Comprehensive error reporting.

ICaptureService Interface

Manages fingerprint capture operations.

StartCaptureAsync Method

Task StartCaptureAsync(int Timeout = 10, int MinimumQuality = 60)

Purpose: Initiates fingerprint capture process.

Parameters:

- Timeout: Maximum capture duration in milliseconds.
- MinimumQuality: Required quality threshold (1-100).

Returns:

- CaptureViewModel containing:
 - Captured fingerprint data.
 - Quality metrics.
 - Capture status.

Features:

- Quality control.
- Timeout management.
- Auto-capture on quality achievement.
- License validation.

StopCaptureAsync Method

Task StopCaptureAsync()

Purpose: Forcefully stops ongoing capture process.

Returns:

- Status code indicating stop success/failure.

Features:

- Immediate capture termination.
- Resource cleanup.
- Device state reset.

Implementation Requirements

System Requirements

- Valid SDK license.
- Compatible fingerprint device.
- Database configuration for search/enrollment operations.

Technical Requirements

- HTTP client for device communication.
- Async operation support.
- Database connectivity.
- Proper error handling implementation.

Best Practices

- Always initialize device before capture.
- Implement proper error handling.
- Check license status before operations.
- Manage device resources properly.
- Use appropriate quality thresholds.
- Implement proper group management.
- Handle timeouts appropriately.

Usage Examples

Basic Device Initialization

```
IDevice deviceService = new DeviceService(httpClient, logger);  
await deviceService.Init("DeviceName");
```

Fingerprint Capture

```
ICaptureService captureService = new  
FingerprintCapturingService(httpClient);  
var captureResult = await captureService.StartCaptureAsync(timeout:  
15, minimumQuality: 75);
```

Search Implementation

```
ISearch searchService = new SearchService(configuration);  
var searchResults = await  
searchService.Search(captureResult.FingerprintData, "GroupA");
```

End of Documentation